



Mx100/Mx200 Software Update



Two files are required to update the Mx digital readout: *update.zip* and *build.prop*. These two files should be placed at the root location of a supported USB Flash Drive (FAT16 or FAT32)

Procedure

- ✓ Insert the USB Flash Drive into the USB port of the readout.
- ✓ Enter the Setup Menu via the Mx button (top left corner or *softkey* menu).
- ✓ Navigate to the Password menu item and enter the Mx readout password (111004).
- ✓ Navigate to the System Menu.
- ✓ From the System Menu select the item *Check For Updates*. The system will initiate the update process.

IMPORTANT: During the Update process please ensure that power is not disconnected from the readout. Allow the update process to finish completely, including readout reboot. Once the update process is complete, verify that the new version of software has been successfully loaded by going to the Mx About menu (Mx Button), and verifying the correct software version number.



Help and Resources

Please visit the support section at www.metlogix.com for access to MetLogix product documentation.

Watch tutorial videos for popular Mx functions at <http://www.youtube.com/metlogix>

Join the discussion on Facebook, search "MetLogix".

Contacts

175 Canal Street, Suite 503, Manchester, NH 03101 USA

Tel: 603.836.4452

Fax: 603.369.6499

Email: support@metlogix.com

Web: www.metlogix.com

© Copyright 2022 All rights reserved. MetLogix, Inc.



Automation and Metrology International, LLC

1-888-354-2525 | sales@auto-met.com

8808 Tyler Blvd, Mentor, OH 44060 | Request a quote: auto-met.com