


M3 Barcode Scanner Setup



Note

Any standard Windows compatible barcode scanner (*wired* or *wireless*) can be used.

No special setup is required to utilize a barcode scanner for *standard* text entry into the M3.

Any M3 dialog that accepts Windows Keyboard input also accepts barcode scanned input.


Part Execution From Barcode

- ✓ To utilize a barcode scanner for launching M3 Part Programs, the following *metlogix.ini* parameter must be used:

[Options]
RunPartFromBarcode=1
- ✓ When scanning a barcode for part execution, the part program filename will be displayed in the upper left corner of the M3 application window and the program will be automatically executed.

Important: Programs loaded via barcode scan must be located in the default MetLogix Parts directory.

(C:\Users\Public\Documents\MetLogix\Parts)



Help and Resources

Please visit the support section at www.metlogix.com for access to MetLogix product documentation.

Watch tutorial videos for popular Mx functions at <http://www.youtube.com/metlogix>

Join the discussion on Facebook, search "MetLogix".

Contacts

175 Canal Street, Suite 503, Manchester, NH 03101 USA
Tel: 603.836.4452
Fax: 603.369.6499
Email: support@metlogix.com
Web: www.metlogix.com